

Troubleshoot CUCM Database Replication Issues

Contents

[Introduction](#)

[Steps to Diagnose the Database Replication](#)

[Step 1. Verify Database Replication is Broken](#)

[Step 2. Collect the CM Database Status from the Cisco Unified Reporting Page on CUCM](#)

[Step 3. Review the Unified CM Database Report of any Component Flagged as an Error](#)

[Step 4. Check the Individual Components that Use the Utils Diagnose Test Command](#)

[Step 5. Check the Connectivity Status from all the Nodes and Ensure They are Authenticated](#)

[Step 6. The Utils Dbreplication Runtimestate Command Shows out of Sync or not Requested Statuses](#)

[Step 7. Repair All/Selective Tables for Database Replication](#)

[Step 8. Reset the Database Replication from Scratch](#)

[Related Information](#)

Introduction

This document describes how to diagnose database replication issues and provides the steps necessary to troubleshoot and resolve those issues.

Steps to Diagnose the Database Replication

This section describes scenarios in which database replication is broken and provides the troubleshooting methodology in order to diagnose and isolate the problem.

Step 1. Verify Database Replication is Broken

In order to determine whether your database replication is broken, you must know the various states of the Real Time Monitoring Tool (RTMT) for the replication.

Value	Meaning	Description
0	Initialization State	Replication is in the process of setting up. A setup failure can occur if replication is in this state for more than an hour.
1	The Number of replicates is incorrect	Set up is still in progress. This state is rarely seen in versions 6.x and 7.x; in version 5.x, it indicates that the setup is still in progress.
2	Replication is good	Logical connections are established and the tables are matched with the other servers on the cluster.
3	Mismatched tables	Logical connections are established but there is an uncertainty whether the tables match. In versions 6.x and 7.x, all servers could show state 3 even if one server is down in the cluster. This issue can occur because the other servers are unsure whether there is an update to the User Facing Feature (UFF) that has not been passed from the subscriber to the other device in

		the cluster.
4	Setup Failed/Dropped	Server no longer has an active logical connection in order to receive any database table across the network. No replication occurs in this state.

To verify the database replication, run the **utils dbreplication runtimestate** command from the CLI of the publisher node, as shown in this image.

```
admin:utils dbreplication runtimestate

Server Time: Thu Jul 16 04:38:19 EDT 2015

Cluster Replication State: BROADCAST SYNC Completed on 1 servers at: 2014-10-13-14-49
  Last Sync Result: SYNC COMPLETED on 680 tables out of 680
  Sync Status: NO ERRORS
  Use CLI to see detail: 'file view activelog cm/trace/db1/20141013_144322_db1_repl_output_Broadcast.log'

DB Version: ccm10_5_1_10000_7
Repltimeout set to: 300s
PROCESS option set to: 1

Cluster Detailed View from CUCM105Pub (2 Servers):
```

SERVER-NAME	IP ADDRESS	PING (msec)	DB/RPC/ DbMon?	REPL. QUEUE	Replication Group ID	REPLICATION SETUP (RTMT) & Details
CUCM105Sub1	172.18.172.230	0.942	Y/Y/Y	0	(g_3)	(2) Setup Completed
CUCM105Pub	172.18.172.229	0.050	Y/Y/Y	0	(g_2)	(2) Setup Completed

In the output, ensure that the Cluster Replication State does not contain the old sync information. Check the same and use the Timestamp.

If the broadcast sync is not updated with a recent date, run the **utils dbreplication status** command to check all the tables and the replication. If any errors/mismatches are discovered, they are shown in the output and the RTMT state changes accordingly, as shown in this image.

o

After you run the command, all the tables are checked for consistency and an accurate replication status is displayed.



Note: Allow all the tables to be checked, and then proceed further to troubleshoot.

```
admin:utils dbreplication runtimestate

Server Time: Thu Jul 16 04:45:36 EDT 2015

Cluster Replication State: Replication status command started at: 2015-07-16-04-44
  Replication status command COMPLETED 112 tables checked out of 680
  Last Completed Table: dirgroup
  No Errors or Mismatches found.
```

Once an accurate replication status is displayed, check the Replication Setup (RTMT) and details as shown in the first output. You must check the status for every node. If any node has a state other than 2, continue to troubleshoot.

Step 2. Collect the CM Database Status from the Cisco Unified Reporting Page on

CUCM

1. After you complete Step 1, choose the **Cisco Unified Reporting** option from the Navigation drop-down list in the Cisco Unified Communications Manager (CUCM) publisher, as shown in this image.



2. Navigate to **System Reports** and click **Unified CM Database Status** as shown in this image.



3. Generate a new report, click on the **Generate New Report** icon as shown in this image.



4. Wait for the new report to be generated successfully.

CISCO

Cisco Unified Reporting

For Cisco Unified Communications Solutions

Navigation Cisco Unified ReportingGo

admin | About | Logout

System ReportsHelp

System Reports

Report Descriptions

Stale LSCs

UCM Users with out-of-date credential algorithm

Unified CM Cluster Overview

Unified CM Data Summary

Unified CM Database Replication Debug

Unified CM Database Status

Unified CM Device Counts Summary

Unified CM Device Distribution Summary

Unified CM Directory URI and GDPR Duplicates

Unified CM Extension

OK: Report generated successfully.

Unified CM Database Status

Provides a snapshot of the Unified CM database health. This report can be useful to monitor periodically, and should be used to ensure the database is healthy before an upgrade.

Created on Tue Nov 12 13:36:01 CST 2024

Unified CM Cluster Name

Cluster Name	Publisher Name/IP
StandAloneCluster	cucm15pub

Unified CM Database Access

Local and publisher databases accessible.

[View Details](#)

Download

Download

Download

5. Once it is generated, Click on the icon to Download the report and **save** it so that it can be provided to a TAC engineer in case a service request (SR) needs to be opened.



Step 3. Review the Unified CM Database Report of any Component Flagged as an Error

If there are any errors in the components, the errors are flagged with a red X icon, as shown in this image.



- Ensure Local and Publisher databases are accessible.
- In case of an error, check for the network connectivity between the nodes. Verify if the A Cisco DB service runs from the CLI of the node and uses the **utils service list** command.
- If the A Cisco DB service is down, run the **utils service start A Cisco DB** command to start the service. If this fails, contact Cisco TAC.
- Ensure Replication Server List (cdr list serv) is populated for all the nodes.

This image illustrates an ideal output.

[View Details](#)

Server	cdr list serv					
SERVER	ID	STATE	STATUS	QUEUE	CONNECTION	CHANGED
172.18.172.229	g_2_ccm10_5_1_10000_7	2 Active	Local	0		
	g_3_ccm10_5_1_10000_7	3 Active	Connected	0	Jul 12 17:37:10	
SERVER	ID	STATE	STATUS	QUEUE	CONNECTION	CHANGED
172.18.172.230	g_2_ccm10_5_1_10000_7	2 Active	Connected	0	Jul 12 17:37:09	
	g_3_ccm10_5_1_10000_7	3 Active	Local	0		

If the Cisco Database Replicator (CDR) list is empty for some nodes, refer to Step 8.

- Ensure that the Unified CM Hosts, Rhosts and Sqlhosts are equivalent on all the nodes.

This is an important step. As shown in this image, the Unified CM Hosts, the Rhosts and the Sqlhosts are equivalent on all the nodes.

Unified CM Hosts



All servers have equivalent host files

[View Details](#)

Unified CM Rhosts



All servers have equivalent rhosts files.

[View Details](#)

Unified CM Sqlhosts



All servers have equivalent sqlhosts files.

[View Details](#)

The Hosts files are mismatched:

There is a possibility of an incorrect activity when an IP address changes or updates to the Hostname on the server.

Refer to this link in order to change IP address to the Hostname for the CUCM.

[IP Address and Hostname Changes](#)

Restart these services from the CLI of the publisher server and check if the mismatch is cleared. If yes, go to Step 8. If no, contact Cisco TAC. Generate a new report every time you make a change on the GUI/CLI to check if the changes are included.

```
Cluster Manager ( utils service restart Cluster Manager)
A Cisco DB ( utils service restart A Cisco DB)
```

The Rhosts files are mismatched:

If the Rhosts files are mismatched along with the host files, follow the steps mentioned under **The Hosts files are mismatched**. If only the Rhosts files are mismatched, run the commands from the CLI:

```
A Cisco DB ( utils service restart A Cisco DB )
Cluster Manager ( utils service restart Cluster Manager)
```

Generate a new report and check if the Rhost files are equivalent on all the servers. If yes, go to Step 8. If no, contact Cisco TAC.

The Sqlhosts are mismatched:

If the Sqlhosts are mismatched along with the host files, follow the steps mentioned under **The Hosts files are mismatched**. If only the Sqlhosts files are mismatched, run the command from the CLI:

```
utils service restart A Cisco DB
```

Generate a new report and check if the Sqlhost files are equivalent on all the servers. If yes, go to Step 8. If no, contact Cisco TAC

- Ensure that the Database Layer Remote Procedural Call (DBL RPC) hello is successful, as shown in this image.

Unified CM DBL RPC Service

[View Details](#)

Server ▲▼	dbl rpchello 'nodename' ▲▼
172.18.172.229	DBL RPCHELLO 172.18.172.229 DBL XML-RPC Server Version 1.1 [8467] [OK]
172.18.172.230	DBL RPCHELLO 172.18.172.230 DBL XML-RPC Server Version 1.1 [29546] [OK]

If the RPC hello does not work for a particular node:

- Ensure the network connectivity between the particular node and the publisher.
- Ensure that the port number 1515 is allowed on the network.

Refer to this link for details on TCP/UDP port usage:

[Cisco Unified Communications Manager TCP and UDP port usage](#)

- Ensure that the network connectivity is successful between the nodes, as shown in this image:

- Unified CM Connectivity

✓ Connectivity Success for 172.18.172.229

✓ Connectivity Success for 172.18.172.230

[View Details](#)

Server ▲▼	1=Success, 0=In Progress, -1=Error : followed by error code ▲▼
172.18.172.229	1 :0
172.18.172.230	1 :0

If the network connectivity fails for the nodes:

- Ensure that the network reachability is present between the nodes.
- Ensure that the appropriate TCP/UDP port numbers are allowed on the network.

Generate a new report, and check for a successful connection. In case of an unsuccessful connection, go to Step 8.


Step 4. Check the Individual Components that Use the Utils Diagnose Test Command

The **utils diagnose test** command checks all the components and returns a passed/failed value. The components that are essential for the proper functioning of the database replication are:

- Network Connectivity:

The **validate_network** command checks all aspects of the network connectivity with all the nodes in the cluster. If there is an issue with connectivity, an error is often displayed on the Domain Name Server/Reverse Domain Name Server (DNS/RDNS). The **validate_network** command completes the operation in 300 seconds. The common error messages as seen in the network connectivity tests:

1. Error "Intra-cluster communication is broken", as shown in this image.



- Cause

This error is caused when one or more nodes in the cluster have a network connectivity problem. Ensure that all the nodes have ping reachability.

- Effect

If the intra-cluster communication is broken, database replication issues occur.

2. Reverse DNS lookup failed.

- Cause

This error is caused when the reverse DNS lookup fails on a node. However, you can verify whether the DNS is configured and functions properly when you use these commands:

`utils network eth0 all` - Shows the DNS configuration (if present)

`utils network host <ip address/Hostname>` - Checks for resolution of ip address/Hostname

- Effect

If the DNS does not function correctly, it can cause database replication issues when the servers are defined and use the hostnames.

- Network Time Protocol (NTP) Reachability:

The NTP is responsible to keep the server's time in sync with the reference clock. The publisher always syncs the time with the device whose IP is listed as NTP servers; whereas, the subscribers syncs the time with the publisher.

It is extremely important for the NTP to be fully functional in order to avoid any database replication issues.

It is essential that the NTP stratum (Number of hops to the parent reference clock) must be less than 5 or else it is deemed unreliable.

Complete these steps in order to check NTP status:

1. Use the **utils diagnose test** command to check the output, as shown in this image.

```
test - ntp_reachability      : Passed
test - ntp_clock_drift       : Passed
test - ntp_stratum           : Passed
```

2. Additionally, you can run this command:

```
utils ntp status
```

```
ntpd (pid 6614) is running...

      remote           refid      st t when poll reach   delay   offset  jitter
=====
*172.18.108.15    .GPS.          1 u 1016 1024  377    0.511   -0.168   0.459

synchronised to NTP server (172.18.108.15) at stratum 2
   time correct to within 45 ms
   polling server every 1024 s

Current time in UTC is : Mon Jul 20 10:18:01 UTC 2015
Current time in America/New_York is : Mon Jul 20 06:18:01 EDT 2015
```

Step 5. Check the Connectivity Status from all the Nodes and Ensure They are Authenticated

1. After you complete Step 4, if there are no issues reported, run the **utils network connectivity** command on all the nodes to check the connectivity to the databases is successful, as shown in this image.

```
admin:utils network connectivity

This command can take up to 3 minutes to complete.
Continue (y/n)?y
Running test, please wait ...
.
Network connectivity test with CUCM105Pub completed successfully.
```

2. If you receive "Cannot send TCP/UDP packets" as an error message, check your network for any retransmissions or block the TCP/UDP ports. The **show network cluster** command checks for authentication of all nodes.

3. If the status of the node is unauthenticated, ensure that the network connectivity and the security password is the same on all the nodes, as shown in this image.

```

admin:show network cluster
172.18.172.230 CUCM105Sub1 Subscriber callmanager DBSub not authenticated - INITIATOR since Mon Jul 20 06:07:34 2015
172.18.172.229 CUCM105Pub Publisher callmanager DBPub authenticated

Server Table (processnode) Entries
-----
172.18.172.229
172.18.172.230

Successful

```

Refer to the links to change/recover the security passwords:

[How to Reset Passwords on CUCM](#)

[CUCM Operating System Administrator Password Recovery](#)

Step 6. The Utils Dbreplication Runtimestate Command Shows out of Sync or not Requested Statuses

It is important to understand that the database replication is a network intensive task as it pushes the actual tables to all the nodes in the cluster. Ensure that:

- The nodes are in the same Data Center/Site: All the nodes are reachable with a lower Round Trip Time (RTT). If the RTT is unusually high, check network performance.
- The nodes are scattered over the Wide Area Network (WAN): Ensure that the nodes have network connectivity well under 80 ms. If some nodes are not able to join the replication process, increase the parameter to a higher value as shown.

utils dbreplication setprocess <1-40>

 **Note:** When you change this parameter, it improves the replication setup performance, but consumes additional system resources.

- The replication timeout is based on the number of nodes in the cluster: The replication timeout (Default: 300 Seconds) is the time that the publisher waits for all the subscribers in order to send their defined messages. Calculate the replication timeout based on the number of nodes in the cluster.

<#root>

Server 1-5 = 1 Minute Per Server

Servers 6-10 = 2 Minutes Per Server

Servers >10 = 3 Minutes Per Server.

<#root>

Example: 12 Servers in Cluster : Server 1-5 * 1 min = 5 min, + 6-10 * 2 min = 10 min, + 11-12 * 3 min =

Repltimeout should be set to 21 Minutes.

Commands to check/set the replication timeout:

```
show tech repltimeout ( To check the current replication timeout value )
utils dbreplication setrepltimeout ( To set the replication timeout )
```

Steps 7 and 8 must be performed after the checklist is fulfilled:

Checklist:

- All the nodes have the connectivity to each other. Refer to Step 5.
- RPC is reachable. Refer to Step 3.
- Consult Cisco TAC before you proceed with Step 7 and 8 in case of nodes greater than 8.
- Perform the procedure in the off business hours.

Step 7. Repair All/Selective Tables for Database Replication

If the **utils dbreplication runtimestate** command shows that there are error/mismatched tables, run the command:

```
Utils dbreplication repair all
```

Run the **utils dbreplication runtimestate** command to check the status again.

Proceed to Step 8, if the status does not change.

Step 8. Reset the Database Replication from Scratch

Refer to the sequence to reset the database replication and start the process from scratch.

```
utils dbreplication stop all (Only on the publisher)
utils dbreplication dropadmindb (First on all the subscribers one by one then the publisher)
utils dbreplication reset all ( Only on the publisher )
```

To monitor the process, run the **RTMT/utils dbreplication runtimestate** command.

Refer to the sequence to reset the database replication for a particular node:

```
utils dbreplication stop <sub name/IP> (Only on the publisher)
utils dbreplication dropadmindb (Only on the affected subscriber)
utils dbreplication reset <sub name/IP> (Only on the publisher )
```

In case you reach Cisco TAC for further assistance, ensure that these outputs and the reports are provided:

```
utils dbreplication runtimestate
utils diagnose test
utils network connectivity
```

Reports:

- The Cisco Unified Reporting CM Database Report (Refer to Step 2).
- The **utils create report database** command from CLI. Download the .tar file and use a SFTP server.

```
admin:utils create report database

Created /var/log/active/cm/log/informix/CUCM105Pub_db_report_Jul_20_15_06_36 for log collection...

Collecting database logs, please be patient...

Collecting message logs (ccm.log) and assert failure files (af files)...
Collecting ris and ats files...
Collecting DB Replication logs...
Collecting DB install logs...
Collecting dblrpc and dbmon logs...
Collecting CDR information...

COMPLETED! Database report created successfully...

To retrieve the CUCM105Pub_db_report_Jul_20_15_06_36.tar, use CLI command:
file get activelog cm/log/informix/CUCM105Pub_db_report_Jul_20_15_06_36.tar

To delete the CUCM105Pub_db_report_Jul_20_15_06_36.tar, use CLI command:
file delete activelog cm/log/informix/CUCM105Pub_db_report_Jul_20_15_06_36.tar
```

Related Information

- [Understanding the Output of utils dbreplication runtimestate for CUCM](#)
- [Troubleshooting CUCM Database Replication Linux Appliance Model](#)
- [CX Delivery Data Protection & Privacy](#)